

```

! FM_rational 1.3                                David M. Smith                                Rational Arithmetic

! This module extends the definition of basic Fortran arithmetic and function operations so
! they also apply to multiple precision rationals, using version 1.3 of FM.
! The multiple precision rational data type is called
!   TYPE (FM_RATIONAL)

! Each FM rational number A/B consists of two values, with A and B being TYPE(IM) integer multiple
! precision numbers.  Negative rationals are represented with A being negative.

! This module supports assignment, arithmetic, comparison, and functions involving FM_RATIONAL
! numbers.

! Mixed-mode operations, such as adding FM_RATIONAL to IM or machine integer types, are supported.
! In general, operations where both the arguments and results are mathematically rational (machine
! precision integers, TYPE(IM), or TYPE (FM_RATIONAL)) are supported, such as A = 1, A = B - 3, or
! A = B / X_IM, where A and B are FM_RATIONAL, and X_IM is type IM.

! Array operations are also supported, so A, B, and X_IM could be 1- or 2-dimensional arrays in the
! examples above.

! Mixed-mode comparisons are also supported, as with IF (A == 1), IF (A <= B - 3), or
! IF (A > B / X_IM).

! TO_FM_RATIONAL is a function for creating a number of type FM_RATIONAL.
! This function can have one argument, for the common case of creating a rational number with an
! integer value.  For TO_FM_RATIONAL(A), A can be a machine integer or array of integers, a type
! IM value or array, or a character string.

! There is also a two argument form, TO_FM_RATIONAL(A,B), that can be used to create the fraction
! A/B when A and B are both machine precision integers, TYPE(IM) multiple precision integers, or
! character strings representing integers.

! The one argument character form can be used with a single input string having both parts of the
! fraction present and separated by '/', as in TO_FM_RATIONAL(' 41 / 314 ').  This might be more
! readable than the equivalent forms TO_FM_RATIONAL( 41, 314 ) or TO_FM_RATIONAL( '41', '314' ).

! The TO_FM function from the basic FM package has been extended to convert a type FM_RATIONAL to
! a type FM number.  The result is an approximation accurate to the current FM precision.

! RATIONAL_APPROX(A, DIGITS) is a function that converts an FM number A to a rational approximation
! of type FM_RATIONAL that has no more than DIGITS decimal digits in the top and bottom.
! Ex:  A = pi, DIGITS = 2   returns the FM_RATIONAL result    22 /    7
!      A = pi, DIGITS = 3   returns the FM_RATIONAL result   355 /   113
!      A = pi, DIGITS = 6   returns the FM_RATIONAL result  833719 / 265381
! The rational result usually approximates A to about 2*DIGITS significant digits, so
! DIGITS should not be more than about half the precision carried for A.
! Ex:  833719 / 265381 = 3.141592653581077771204419306..., and agrees with pi to about 11 s.d.

! The standard Fortran functions that are available for FM_RATIONAL arguments are the ones that
! give exact rational results.  So if A and B are type FM_RATIONAL variables, A**B, EXP(A), etc.,

```

! are not provided since the results are not generally exact rational numbers.

! But INT(A), FLOOR(A), MAX(A,B), MOD(A,B), etc., do give rational result and are provided.

! AVAILABLE OPERATONS:

!
! =
! +
! -
! *
! /
! ** A ** J is provided for FM_RATIONAL A and machine integer J.
! ==
! /=
! <
! <=
! >
! >=
! ABS(A)
! CEILING(A)
! DIM(A,B) Positive difference. Returns A - B if A > B, zero if not.
! FLOOR(A)
! INT(A)
! IS_UNKNOWN(A) Returns true if A is unknown.
! MAX(A,B,...) Can have from 2 to 10 arguments.
! MIN(A,B,...) Can have from 2 to 10 arguments.
! MOD(A,B) Result is A - int(A/B) * B
! MODULO(A,B) Result is A - floor(A/B) * B
! NINT(A)

! Array operations for functions.

! ABS, CEILING, FLOOR, INT, and NINT can each have a 1- or 2-dimensional array argument.
! They will return a vector or matrix with the function applied to each element of the
! argument.

! DIM, MOD, MODULO work the same way, but the two array arguments for these functions must
! have the same size and shape.

! IS_UNKNOWN is a logical function that can be used with an array argument but does not return
! an array result. It returns "true" if any element of the input array is FM's special UNKNOWN
! value, which comes from undefined operations such as dividing by zero.

! Functions that operate only on arrays.

! DOT_PRODUCT(X,Y) Dot product of rank 1 vectors.
! MATMUL(X,Y) Matrix multiplication of arrays
! Cases for valid argument shapes:
! (1) (n,m) * (m,k) --> (n,k)
! (2) (m) * (m,k) --> (k)
! (3) (n,m) * (m) --> (n)
! MAXVAL(X) Maximum value in the array
! MINVAL(X) Minimum value in the array
! PRODUCT(X) Product of all values in the array
! SUM(X) Sum of all values in the array
! TRANSPOSE(X) Matrix transposition. If X is a rank 2 array with shape (n,m), then

! $Y = \text{TRANSPOSE}(X)$ has shape (m,n) with $Y(i,j) = X(j,i)$.

USE FMZM

TYPE FM_RATIONAL

INTEGER :: NUMERATOR = -1

INTEGER :: DENOMINATOR = -1

END TYPE

! Work variables for derived type operations.

TYPE (IM), SAVE :: R_1 = IM(-3), R_2 = IM(-3), R_3 = IM(-3), R_4 = IM(-3), &
R_5 = IM(-3), R_6 = IM(-3)

TYPE (FM), SAVE :: F_1 = FM(-3), F_2 = FM(-3)

TYPE (FM_RATIONAL), SAVE :: MT_RM = FM_RATIONAL(-3,-3), MU_RM = FM_RATIONAL(-3,-3)

INTEGER, SAVE :: RATIONAL_EXP_MAX = 0, RATIONAL_SKIP_MAX = 100

LOGICAL, SAVE :: SKIP_GCD = .FALSE.

INTERFACE TO_FM_RATIONAL

MODULE PROCEDURE FM_RATIONAL_I

MODULE PROCEDURE FM_RATIONAL_II

MODULE PROCEDURE FM_RATIONAL_I1

MODULE PROCEDURE FM_RATIONAL_I2

MODULE PROCEDURE FM_RATIONAL_IM

MODULE PROCEDURE FM_RATIONAL_IMIM

MODULE PROCEDURE FM_RATIONAL_IM1

MODULE PROCEDURE FM_RATIONAL_IM2

MODULE PROCEDURE FM_RATIONAL_ST

MODULE PROCEDURE FM_RATIONAL_STST

END INTERFACE

INTERFACE FM_UNDEF_INP

MODULE PROCEDURE FM_UNDEF_INP_RATIONAL_RM0

MODULE PROCEDURE FM_UNDEF_INP_RATIONAL_RM1

MODULE PROCEDURE FM_UNDEF_INP_RATIONAL_RM2

END INTERFACE

INTERFACE FMEQ_INDEX_RATIONAL

MODULE PROCEDURE FMEQ_INDEX_RATIONAL_RM0

MODULE PROCEDURE FMEQ_INDEX_RATIONAL_RM1

MODULE PROCEDURE FMEQ_INDEX_RATIONAL_RM2

END INTERFACE

INTERFACE RATIONAL_NUMERATOR

MODULE PROCEDURE RATIONAL_NUMERATOR_IM

END INTERFACE

INTERFACE RATIONAL_DENOMINATOR

MODULE PROCEDURE RATIONAL_DENOMINATOR_IM

END INTERFACE

INTERFACE FM_DEALLOCATE

MODULE PROCEDURE FM_DEALLOCATE_RM1

MODULE PROCEDURE FM_DEALLOCATE_RM2

END INTERFACE

```

INTERFACE ASSIGNMENT (=)
  MODULE PROCEDURE FMEQ_RATIONAL_RMRM
  MODULE PROCEDURE FMEQ_RATIONAL_RMI
  MODULE PROCEDURE FMEQ_RATIONAL_RMIM

  MODULE PROCEDURE FMEQ_RATIONAL_RM1RM
  MODULE PROCEDURE FMEQ_RATIONAL_RM1RM1
  MODULE PROCEDURE FMEQ_RATIONAL_RM1I
  MODULE PROCEDURE FMEQ_RATIONAL_RM1I1
  MODULE PROCEDURE FMEQ_RATIONAL_RM1IM
  MODULE PROCEDURE FMEQ_RATIONAL_RM1IM1

  MODULE PROCEDURE FMEQ_RATIONAL_RM2RM
  MODULE PROCEDURE FMEQ_RATIONAL_RM2RM2
  MODULE PROCEDURE FMEQ_RATIONAL_RM2I
  MODULE PROCEDURE FMEQ_RATIONAL_RM2I2
  MODULE PROCEDURE FMEQ_RATIONAL_RM2IM
  MODULE PROCEDURE FMEQ_RATIONAL_RM2IM2
END INTERFACE

```

CONTAINS

!

TO_FM_RATIONAL

```

FUNCTION FM_RATIONAL_I(TOP)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: FM_RATIONAL_I
  INTEGER :: TOP,N1,N2
  INTENT (IN) :: TOP
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  IF (TOP == 0) THEN
    CALL IMST2M('0',FM_RATIONAL_I%NUMERATOR)
    CALL IMST2M('1',FM_RATIONAL_I%DENOMINATOR)
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
  ENDIF
  N1 = ABS(TOP)
  N2 = 1
  IF (TOP > 0) THEN
    CALL IMI2M(N1,FM_RATIONAL_I%NUMERATOR)
  ELSE
    CALL IMI2M(-N1,FM_RATIONAL_I%NUMERATOR)
  ENDIF
  CALL IMI2M(N2,FM_RATIONAL_I%DENOMINATOR)
  CALL FM_MAX_EXP_RM(FM_RATIONAL_I)
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_RATIONAL_I

```

```

FUNCTION FM_RATIONAL_II(TOP,BOT)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: FM_RATIONAL_II
  INTEGER :: TOP,BOT,N1,N2
  INTENT (IN) :: TOP,BOT
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1

```

```

IF (BOT == 0) THEN
  CALL IMST2M('UNKNOWN',FM_RATIONAL_II%NUMERATOR)
  CALL IMST2M('UNKNOWN',FM_RATIONAL_II%DENOMINATOR)
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
  RETURN
ENDIF
IF (TOP == 0) THEN
  CALL IMST2M('0',FM_RATIONAL_II%NUMERATOR)
  CALL IMST2M('1',FM_RATIONAL_II%DENOMINATOR)
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
  RETURN
ENDIF
N1 = ABS(TOP)
N2 = ABS(BOT)
CALL FMGCDI(N1,N2)
IF ((TOP > 0 .AND. BOT > 0) .OR. (TOP < 0 .AND. BOT < 0)) THEN
  CALL IMI2M(N1,FM_RATIONAL_II%NUMERATOR)
ELSE
  CALL IMI2M(-N1,FM_RATIONAL_II%NUMERATOR)
ENDIF
CALL IMI2M(N2,FM_RATIONAL_II%DENOMINATOR)
CALL FM_MAX_EXP_RM(FM_RATIONAL_II)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_RATIONAL_II

```

```

FUNCTION FM_RATIONAL_I1(IVAL)
  USE FMVALS
  IMPLICIT NONE
  INTEGER, DIMENSION(:) :: IVAL
  TYPE (FM_RATIONAL), DIMENSION(SIZE(IVAL)) :: FM_RATIONAL_I1
  INTEGER :: J
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  DO J = 1, SIZE(IVAL)
    CALL IMI2M(IVAL(J),FM_RATIONAL_I1(J)%NUMERATOR)
    CALL IMI2M(1,FM_RATIONAL_I1(J)%DENOMINATOR)
    CALL FM_MAX_EXP_RM(FM_RATIONAL_I1(J))
  ENDDO
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_RATIONAL_I1

```

```

FUNCTION FM_RATIONAL_I2(IVAL)
  USE FMVALS
  IMPLICIT NONE
  INTEGER, DIMENSION(:,:) :: IVAL
  TYPE (FM_RATIONAL), DIMENSION(SIZE(IVAL,DIM=1),SIZE(IVAL,DIM=2)) :: FM_RATIONAL_I2
  INTEGER :: J,K
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  DO J = 1, SIZE(IVAL,DIM=1)
    DO K = 1, SIZE(IVAL,DIM=2)
      CALL IMI2M(IVAL(J,K),FM_RATIONAL_I2(J,K)%NUMERATOR)
      CALL IMI2M(1,FM_RATIONAL_I2(J,K)%DENOMINATOR)
      CALL FM_MAX_EXP_RM(FM_RATIONAL_I2(J,K))
    ENDDO
  ENDDO
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_RATIONAL_I2

```

```

FUNCTION FM_RATIONAL_IM(TOP)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: FM_RATIONAL_IM
  INTEGER :: R_SIGN
  TYPE (IM) :: TOP
  INTENT (IN) :: TOP
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  CALL FM_UNDEF_INP(TOP)
  CALL IMEQ(TOP%MIM,R_1%MIM)
  CALL IMI2M(1,R_2%MIM)
  IF (IS_UNKNOWN(R_1) .OR. IS_OVERFLOW(R_1)) THEN
    CALL IMST2M('UNKNOWN',FM_RATIONAL_IM%NUMERATOR)
    CALL IMST2M('UNKNOWN',FM_RATIONAL_IM%DENOMINATOR)
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
  ENDIF
  IF (R_1 == 0) THEN
    CALL IMST2M('0',FM_RATIONAL_IM%NUMERATOR)
    CALL IMST2M('1',FM_RATIONAL_IM%DENOMINATOR)
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
  ENDIF
  R_SIGN = 1
  IF (R_1 < 0) THEN
    R_SIGN = -1
  ENDIF
  CALL IM_ABS(R_1,R_4)
  CALL IM_ABS(R_2,R_5)
  CALL FM_MAX_EXP_IM(R_4,R_5)
  IF (SKIP_GCD .AND. MAX(MWK(START(R_4%MIM)+2),MWK(START(R_5%MIM)+2)) < RATIONAL_SKIP_MAX) THEN
    IF (R_SIGN == -1) MWK(START(R_4%MIM)) = -1
    CALL IMEQ(R_4%MIM,FM_RATIONAL_IM%NUMERATOR)
    CALL IMEQ(R_5%MIM,FM_RATIONAL_IM%DENOMINATOR)
  ELSE
    CALL IM_GCD(R_4,R_5,R_3)
    CALL IM_DIV(R_4,R_3,R_1)
    CALL IM_DIV(R_5,R_3,R_2)
    IF (R_SIGN == -1) MWK(START(R_1%MIM)) = -1
    CALL IMEQ(R_1%MIM,FM_RATIONAL_IM%NUMERATOR)
    CALL IMEQ(R_2%MIM,FM_RATIONAL_IM%DENOMINATOR)
  ENDIF
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_RATIONAL_IM

```

```

FUNCTION FM_RATIONAL_IMIM(TOP,BOT)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: FM_RATIONAL_IMIM
  INTEGER :: R_SIGN
  TYPE (IM) :: TOP,BOT
  INTENT (IN) :: TOP,BOT
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  CALL FM_UNDEF_INP(TOP)
  CALL FM_UNDEF_INP(BOT)

```

```

CALL IMEQ(TOP%MIM,R_1%MIM)
CALL IMEQ(BOT%MIM,R_2%MIM)
IF (R_2 == 0 .OR. IS_UNKNOWN(R_1) .OR. IS_OVERFLOW(R_1) .OR. &
    IS_UNKNOWN(R_2) .OR. IS_OVERFLOW(R_2) ) THEN
    CALL IMST2M('UNKNOWN',FM_RATIONAL_IMIM%NUMERATOR)
    CALL IMST2M('UNKNOWN',FM_RATIONAL_IMIM%DENOMINATOR)
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
ENDIF
IF (R_1 == 0) THEN
    CALL IMST2M('0',FM_RATIONAL_IMIM%NUMERATOR)
    CALL IMST2M('1',FM_RATIONAL_IMIM%DENOMINATOR)
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
ENDIF
R_SIGN = 1
IF ((R_1 > 0 .AND. R_2 < 0) .OR. (R_1 < 0 .AND. R_2 > 0)) THEN
    R_SIGN = -1
ENDIF
CALL IM_ABS(R_1,R_4)
CALL IM_ABS(R_2,R_5)
CALL FM_MAX_EXP_IM(R_4,R_5)
IF (SKIP_GCD .AND. MAX(MWK(START(R_4%MIM)+2),MWK(START(R_5%MIM)+2)) < RATIONAL_SKIP_MAX) THEN
    IF (R_SIGN == -1) MWK(START(R_4%MIM)) = -1
    CALL IMEQ(R_4%MIM,FM_RATIONAL_IMIM%NUMERATOR)
    CALL IMEQ(R_5%MIM,FM_RATIONAL_IMIM%DENOMINATOR)
ELSE
    CALL IM_GCD(R_4,R_5,R_3)
    CALL IM_DIV(R_4,R_3,R_1)
    CALL IM_DIV(R_5,R_3,R_2)
    IF (R_SIGN == -1) MWK(START(R_1%MIM)) = -1
    CALL IMEQ(R_1%MIM,FM_RATIONAL_IMIM%NUMERATOR)
    CALL IMEQ(R_2%MIM,FM_RATIONAL_IMIM%DENOMINATOR)
ENDIF
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_RATIONAL_IMIM

FUNCTION FM_RATIONAL_IM1(TOP)
    USE FMVALS
    IMPLICIT NONE
    TYPE (IM), DIMENSION(:) :: TOP
    TYPE (FM_RATIONAL), DIMENSION(SIZE(TOP)) :: FM_RATIONAL_IM1
    INTEGER :: J
    TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
    DO J = 1, SIZE(TOP)
        CALL IMEQ(TOP(J)%MIM,FM_RATIONAL_IM1(J)%NUMERATOR)
        CALL IMI2M(1,FM_RATIONAL_IM1(J)%DENOMINATOR)
        CALL FM_MAX_EXP_RM(FM_RATIONAL_IM1(J))
    ENDDO
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_RATIONAL_IM1

FUNCTION FM_RATIONAL_IM2(TOP)
    USE FMVALS
    IMPLICIT NONE
    TYPE (IM), DIMENSION(:,:) :: TOP

```

```

TYPE (FM_RATIONAL), DIMENSION(SIZE(TOP,DIM=1),SIZE(TOP,DIM=2)) :: FM_RATIONAL_IM2
INTEGER :: J,K
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
DO J = 1, SIZE(TOP,DIM=1)
  DO K = 1, SIZE(TOP,DIM=2)
    CALL IMEQ(TOP(J,K)%MIM,FM_RATIONAL_IM2(J,K)%NUMERATOR)
    CALL IMI2M(1,FM_RATIONAL_IM2(J,K)%DENOMINATOR)
    CALL FM_MAX_EXP_RM(FM_RATIONAL_IM2(J,K))
  ENDDO
ENDDO
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_RATIONAL_IM2

FUNCTION FM_RATIONAL_ST(TOP)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: FM_RATIONAL_ST
  INTEGER :: K,R_SIGN
  CHARACTER(*) :: TOP
  INTENT (IN) :: TOP
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  K = INDEX(TOP, '/')
  IF (K > 0) THEN
    CALL IMST2M(TOP(1:K-1),R_1%MIM)
    CALL IMST2M(TOP(K+1:LEN(TOP)),R_2%MIM)
  ELSE
    CALL IMST2M(TOP,R_1%MIM)
    CALL IMI2M(1,R_2%MIM)
  ENDIF
  IF (R_2 == 0 .OR. IS_UNKNOWN(R_1) .OR. IS_OVERFLOW(R_1) .OR. &
      IS_UNKNOWN(R_2) .OR. IS_OVERFLOW(R_2) ) THEN
    CALL IMST2M('UNKNOWN',FM_RATIONAL_ST%NUMERATOR)
    CALL IMST2M('UNKNOWN',FM_RATIONAL_ST%DENOMINATOR)
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
  ENDIF
  IF (R_1 == 0) THEN
    CALL IMST2M('0',FM_RATIONAL_ST%NUMERATOR)
    CALL IMST2M('1',FM_RATIONAL_ST%DENOMINATOR)
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
  ENDIF
  R_SIGN = 1
  IF ((R_1 > 0 .AND. R_2 < 0) .OR. (R_1 < 0 .AND. R_2 > 0)) THEN
    R_SIGN = -1
  ENDIF
  CALL IM_ABS(R_1,R_4)
  CALL IM_ABS(R_2,R_5)
  CALL FM_MAX_EXP_IM(R_4,R_5)
  IF (SKIP_GCD .AND. MAX(MWK(START(R_4%MIM)+2),MWK(START(R_5%MIM)+2)) < RATIONAL_SKIP_MAX) THEN
    IF (R_SIGN == -1) MWK(START(R_4%MIM)) = -1
    CALL IMEQ(R_4%MIM,FM_RATIONAL_ST%NUMERATOR)
    CALL IMEQ(R_5%MIM,FM_RATIONAL_ST%DENOMINATOR)
  ELSE
    CALL IM_GCD(R_4,R_5,R_3)
    CALL IM_DIV(R_4,R_3,R_1)
  ENDIF

```



```

    CALL IM_DIV(R_5,R_3,R_2)
    IF (R_SIGN == -1) MWK(START(R_1%MIM)) = -1
    CALL IMEQ(R_1%MIM,FM_RATIONAL_ST%NUMERATOR)
    CALL IMEQ(R_2%MIM,FM_RATIONAL_ST%DENOMINATOR)
ENDIF
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_RATIONAL_ST

FUNCTION FM_RATIONAL_STST(TOP,BOT)
USE FMVALS
IMPLICIT NONE
TYPE (FM_RATIONAL) :: FM_RATIONAL_STST
INTEGER :: R_SIGN
CHARACTER(*) :: TOP,BOT
INTENT (IN) :: TOP,BOT
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL IMST2M(TOP,R_1%MIM)
CALL IMST2M(BOT,R_2%MIM)
IF (R_2 == 0 .OR. IS_UNKNOWN(R_1) .OR. IS_OVERFLOW(R_1) .OR. &
    IS_UNKNOWN(R_2) .OR. IS_OVERFLOW(R_2) ) THEN
    CALL IMST2M('UNKNOWN',FM_RATIONAL_STST%NUMERATOR)
    CALL IMST2M('UNKNOWN',FM_RATIONAL_STST%DENOMINATOR)
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
ENDIF
IF (R_1 == 0) THEN
    CALL IMST2M('0',FM_RATIONAL_STST%NUMERATOR)
    CALL IMST2M('1',FM_RATIONAL_STST%DENOMINATOR)
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
ENDIF
R_SIGN = 1
IF ((R_1 > 0 .AND. R_2 < 0) .OR. (R_1 < 0 .AND. R_2 > 0)) THEN
    R_SIGN = -1
ENDIF
CALL IM_ABS(R_1,R_4)
CALL IM_ABS(R_2,R_5)
CALL FM_MAX_EXP_IM(R_4,R_5)
IF (SKIP_GCD .AND. MAX(MWK(START(R_4%MIM)+2),MWK(START(R_5%MIM)+2)) < RATIONAL_SKIP_MAX) THEN
    IF (R_SIGN == -1) MWK(START(R_4%MIM)) = -1
    CALL IMEQ(R_4%MIM,FM_RATIONAL_STST%NUMERATOR)
    CALL IMEQ(R_5%MIM,FM_RATIONAL_STST%DENOMINATOR)
ELSE
    CALL IM_GCD(R_4,R_5,R_3)
    CALL IM_DIV(R_4,R_3,R_1)
    CALL IM_DIV(R_5,R_3,R_2)
    IF (R_SIGN == -1) MWK(START(R_1%MIM)) = -1
    CALL IMEQ(R_1%MIM,FM_RATIONAL_STST%NUMERATOR)
    CALL IMEQ(R_2%MIM,FM_RATIONAL_STST%DENOMINATOR)
ENDIF
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_RATIONAL_STST

```

!

RATIONAL_NUMERATOR

```

FUNCTION RATIONAL_NUMERATOR_IM(MA)

```

```

USE FMVALS
IMPLICIT NONE
TYPE (FM_RATIONAL) :: MA
TYPE (IM) :: RATIONAL_NUMERATOR_IM
INTENT (IN) :: MA
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL IMEQ(MA%NUMERATOR,RATIONAL_NUMERATOR_IM%MIM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION RATIONAL_NUMERATOR_IM

```

!

RATIONAL_DENOMINATOR

```

FUNCTION RATIONAL_DENOMINATOR_IM(MA)
USE FMVALS
IMPLICIT NONE
TYPE (FM_RATIONAL) :: MA
TYPE (IM) :: RATIONAL_DENOMINATOR_IM
INTENT (IN) :: MA
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL IMEQ(MA%DENOMINATOR,RATIONAL_DENOMINATOR_IM%MIM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION RATIONAL_DENOMINATOR_IM

```

```

SUBROUTINE FM_MAX_EXP_RM(MA)
USE FMVALS
IMPLICIT NONE
TYPE (FM_RATIONAL) :: MA
INTEGER :: NT, NB
NT = MWK(START(MA%NUMERATOR)+2)
NB = MWK(START(MA%DENOMINATOR)+2)
IF (NT < MEXPOV .AND. NT > RATIONAL_EXP_MAX) RATIONAL_EXP_MAX = NT
IF (NB < MEXPOV .AND. NB > RATIONAL_EXP_MAX) RATIONAL_EXP_MAX = NB
END SUBROUTINE FM_MAX_EXP_RM

```

```

SUBROUTINE FM_MAX_EXP_IM(MA,MB)
USE FMVALS
IMPLICIT NONE
TYPE (IM) :: MA,MB
INTEGER :: NT
NT = MWK(START(MA%MIM)+2)
IF (NT < MEXPOV .AND. NT > RATIONAL_EXP_MAX) RATIONAL_EXP_MAX = NT
NT = MWK(START(MB%MIM)+2)
IF (NT < MEXPOV .AND. NT > RATIONAL_EXP_MAX) RATIONAL_EXP_MAX = NT
END SUBROUTINE FM_MAX_EXP_IM

```

!

FM_PRINT_RATIONAL

```

SUBROUTINE FM_PRINT_RATIONAL(MA)
USE FMVALS
IMPLICIT NONE
TYPE (FM_RATIONAL) :: MA
CHARACTER(100) :: ST1, ST2
CHARACTER(203) :: STR
INTENT (IN) :: MA
INTEGER :: J,KPT
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1

```

! If the top and bottom integers can be printed on one line, as 12 / 7
 ! in fewer than KSWIDE characters, do it. Otherwise call IMPRINT twice.

```

CALL IMABS(MA%NUMERATOR,R_1%MIM)
CALL IMABS(MA%DENOMINATOR,R_2%MIM)
CALL IMMPY(R_1%MIM,R_2%MIM,R_3%MIM)

IF (TO_IM(10)**(KSWIDE-11) > R_3 .AND. R_1 < TO_IM('1E+99') .AND. R_2 < TO_IM('1E+99')) THEN
  CALL IMFORM('I100',MA%NUMERATOR,ST1)
  CALL IMFORM('I100',MA%DENOMINATOR,ST2)
  STR = ' '
  KPT = 0
  DO J = 1, 100
    IF (ST1(J:J) /= ' ') THEN
      KPT = KPT + 1
      STR(KPT:KPT) = ST1(J:J)
    ENDIF
  ENDDO
  STR(KPT+1:KPT+3) = ' / '
  KPT = KPT + 3
  DO J = 1, 100
    IF (ST2(J:J) /= ' ') THEN
      KPT = KPT + 1
      STR(KPT:KPT) = ST2(J:J)
    ENDIF
  ENDDO
  IF (MWK(START(MA%NUMERATOR)) < 0) THEN
    WRITE (KW,"(6X,A)") STR(1:KPT)
  ELSE
    WRITE (KW,"(7X,A)") STR(1:KPT)
  ENDIF
ELSE
  CALL IMPRINT(MA%NUMERATOR)
  WRITE (KW,"(A)") ' / '
  CALL IMPRINT(MA%DENOMINATOR)
ENDIF
CALL FMEQ_RATIONAL_TEMP
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END SUBROUTINE FM_PRINT_RATIONAL

```

! FMEQ_INDEX

! Check to see if the multiple precision number MA being defined is previously undefined
 ! and has a default index value of -1. If so, since it is a user variable and not a
 ! compiler-generated temporary number, change the index to -3 so that the variable is
 ! stored in the saved area in MWK and not treated as a temporary variable.

```

SUBROUTINE FMEQ_INDEX_RATIONAL_RM0(MA)
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: MA
  INTENT (INOUT) :: MA
  IF (MA%NUMERATOR == -1) MA%NUMERATOR = -3
  IF (MA%DENOMINATOR == -1) MA%DENOMINATOR = -3
END SUBROUTINE FMEQ_INDEX_RATIONAL_RM0

```

```

SUBROUTINE FMEQ_INDEX_RATIONAL_RM1(MA)
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:) :: MA
  INTEGER :: J
  INTENT (INOUT) :: MA
  DO J = 1, SIZE(MA)
    IF (MA(J)%NUMERATOR == -1) MA(J)%NUMERATOR = -3
    IF (MA(J)%DENOMINATOR == -1) MA(J)%DENOMINATOR = -3
  ENDDO
END SUBROUTINE FMEQ_INDEX_RATIONAL_RM1

SUBROUTINE FMEQ_INDEX_RATIONAL_RM2(MA)
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:, :) :: MA
  INTEGER :: J, K
  INTENT (INOUT) :: MA
  DO J = 1, SIZE(MA, DIM=1)
    DO K = 1, SIZE(MA, DIM=2)
      IF (MA(J, K)%NUMERATOR == -1) MA(J, K)%NUMERATOR = -3
      IF (MA(J, K)%DENOMINATOR == -1) MA(J, K)%DENOMINATOR = -3
    ENDDO
  ENDDO
END SUBROUTINE FMEQ_INDEX_RATIONAL_RM2

SUBROUTINE FM_UNDEF_INP_RATIONAL_RM0(MA)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: MA
  INTENT (IN) :: MA
  IF (MA%NUMERATOR <= 0) CALL FM_INPUT_ERROR
  IF (MA%NUMERATOR > NUMBER_USED .AND. &
    MA%NUMERATOR < LOWEST_SAVED_AREA_INDEX) CALL FM_INPUT_ERROR
  IF (MA%NUMERATOR > SIZE_OF_START) CALL FM_INPUT_ERROR
  IF (MA%DENOMINATOR <= 0) CALL FM_INPUT_ERROR
  IF (MA%DENOMINATOR > NUMBER_USED .AND. &
    MA%DENOMINATOR < LOWEST_SAVED_AREA_INDEX) CALL FM_INPUT_ERROR
  IF (MA%DENOMINATOR > SIZE_OF_START) CALL FM_INPUT_ERROR
END SUBROUTINE FM_UNDEF_INP_RATIONAL_RM0

SUBROUTINE FM_UNDEF_INP_RATIONAL_RM1(MA)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:) :: MA
  INTEGER :: J
  INTENT (IN) :: MA
  DO J = 1, SIZE(MA)
    IF (MA(J)%NUMERATOR <= 0) CALL FM_INPUT_ERROR1(J)
    IF (MA(J)%NUMERATOR > NUMBER_USED .AND. &
      MA(J)%NUMERATOR < LOWEST_SAVED_AREA_INDEX) CALL FM_INPUT_ERROR1(J)
    IF (MA(J)%NUMERATOR > SIZE_OF_START) CALL FM_INPUT_ERROR1(J)
    IF (MA(J)%DENOMINATOR <= 0) CALL FM_INPUT_ERROR1(J)
    IF (MA(J)%DENOMINATOR > NUMBER_USED .AND. &
      MA(J)%DENOMINATOR < LOWEST_SAVED_AREA_INDEX) CALL FM_INPUT_ERROR1(J)
    IF (MA(J)%DENOMINATOR > SIZE_OF_START) CALL FM_INPUT_ERROR1(J)
  ENDDO
END SUBROUTINE FM_UNDEF_INP_RATIONAL_RM1

```

```

SUBROUTINE FM_UNDEF_INP_RATIONAL_RM2(MA)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:,:) :: MA
  INTEGER :: J,K
  INTENT (IN) :: MA
  DO J = 1, SIZE(MA,DIM=1)
    DO K = 1, SIZE(MA,DIM=2)
      IF (MA(J,K)%NUMERATOR <= 0) CALL FM_INPUT_ERROR2(J,K)
      IF (MA(J,K)%NUMERATOR > NUMBER_USED .AND. &
          MA(J,K)%NUMERATOR < LOWEST_SAVED_AREA_INDEX) CALL FM_INPUT_ERROR2(J,K)
      IF (MA(J,K)%NUMERATOR > SIZE_OF_START) CALL FM_INPUT_ERROR2(J,K)
      IF (MA(J,K)%DENOMINATOR <= 0) CALL FM_INPUT_ERROR2(J,K)
      IF (MA(J,K)%DENOMINATOR > NUMBER_USED .AND. &
          MA(J,K)%DENOMINATOR < LOWEST_SAVED_AREA_INDEX) CALL FM_INPUT_ERROR2(J,K)
      IF (MA(J,K)%DENOMINATOR > SIZE_OF_START) CALL FM_INPUT_ERROR2(J,K)
    ENDDO
  ENDDO
END SUBROUTINE FM_UNDEF_INP_RATIONAL_RM2

```

```

SUBROUTINE FMEQ_RATIONAL_TEMP

```

! Check to see if the last few FM numbers are temporaries.
! If so, re-set NUMBER_USED so that space in MWK can be re-claimed.

```

  USE FMVALS
  IMPLICIT NONE
  INTEGER :: J,K,L
  IF (USER_FUNCTION_LEVEL == 0) THEN
    L = 1
  ELSE
    L = NUMBER_USED_AT_LEVEL(USER_FUNCTION_LEVEL) + 1
  ENDIF
  K = NUMBER_USED
  DO J = K, L, -1
    IF (TEMPV(J) == -1 .OR. TEMPV(J) <= -6) THEN
      NUMBER_USED = NUMBER_USED - 1
      TEMPV(J) = -2
    ELSE
      EXIT
    ENDIF
  ENDDO

```

```

END SUBROUTINE FMEQ_RATIONAL_TEMP

```

```

SUBROUTINE FM_DEALLOCATE_RM1(MA)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:) :: MA
  INTEGER :: J
  INTENT (INOUT) :: MA
  DO J = 1, SIZE(MA)
    IF (MA(J)%NUMERATOR >= LOWEST_SAVED_AREA_INDEX) THEN
      TEMPV(MA(J)%NUMERATOR) = -6
      TOTAL_IMTEMP6 = TOTAL_IMTEMP6 + 1
    ENDIF
  ENDDO

```

```

    IF (NMAX_IMTEMP6 >= SIZE_OF_TEMP6) THEN
        N_IMTEMP6 = MOD( TOTAL_IMTEMP6, SIZE_OF_TEMP6 ) + 1
        IMTEMP6(N_IMTEMP6) = MA(J)%NUMERATOR
    ELSE
        NMAX_IMTEMP6 = NMAX_IMTEMP6 + 1
        IMTEMP6(NMAX_IMTEMP6) = MA(J)%NUMERATOR
    ENDIF
ENDIF
ENDIF
IF (MA(J)%DENOMINATOR >= LOWEST_SAVED_AREA_INDEX) THEN
    TEMPV(MA(J)%DENOMINATOR) = -6
    TOTAL_IMTEMP6 = TOTAL_IMTEMP6 + 1
    IF (NMAX_IMTEMP6 >= SIZE_OF_TEMP6) THEN
        N_IMTEMP6 = MOD( TOTAL_IMTEMP6, SIZE_OF_TEMP6 ) + 1
        IMTEMP6(N_IMTEMP6) = MA(J)%DENOMINATOR
    ELSE
        NMAX_IMTEMP6 = NMAX_IMTEMP6 + 1
        IMTEMP6(NMAX_IMTEMP6) = MA(J)%DENOMINATOR
    ENDIF
ENDIF
ENDIF
ENDDO
CALL FMDEFINE_RESIZE(0)
END SUBROUTINE FM_DEALLOCATE_RM1

SUBROUTINE FM_DEALLOCATE_RM2(MA)
    USE FMVALS
    IMPLICIT NONE
    TYPE (FM_RATIONAL), DIMENSION(:, :) :: MA
    INTEGER :: J, K
    INTENT (INOUT) :: MA
    DO J = 1, SIZE(MA, DIM=1)
        DO K = 1, SIZE(MA, DIM=2)
            IF (MA(J, K)%NUMERATOR >= LOWEST_SAVED_AREA_INDEX) THEN
                TEMPV(MA(J, K)%NUMERATOR) = -6
                TOTAL_IMTEMP6 = TOTAL_IMTEMP6 + 1
                IF (NMAX_IMTEMP6 >= SIZE_OF_TEMP6) THEN
                    N_IMTEMP6 = MOD( TOTAL_IMTEMP6, SIZE_OF_TEMP6 ) + 1
                    IMTEMP6(N_IMTEMP6) = MA(J, K)%NUMERATOR
                ELSE
                    NMAX_IMTEMP6 = NMAX_IMTEMP6 + 1
                    IMTEMP6(NMAX_IMTEMP6) = MA(J, K)%NUMERATOR
                ENDIF
            ENDIF
        ENDIF
        IF (MA(J, K)%DENOMINATOR >= LOWEST_SAVED_AREA_INDEX) THEN
            TEMPV(MA(J, K)%DENOMINATOR) = -6
            TOTAL_IMTEMP6 = TOTAL_IMTEMP6 + 1
            IF (NMAX_IMTEMP6 >= SIZE_OF_TEMP6) THEN
                N_IMTEMP6 = MOD( TOTAL_IMTEMP6, SIZE_OF_TEMP6 ) + 1
                IMTEMP6(N_IMTEMP6) = MA(J, K)%DENOMINATOR
            ELSE
                NMAX_IMTEMP6 = NMAX_IMTEMP6 + 1
                IMTEMP6(NMAX_IMTEMP6) = MA(J, K)%DENOMINATOR
            ENDIF
        ENDIF
    ENDIF
ENDDO
ENDDO
CALL FMDEFINE_RESIZE(0)

```

END SUBROUTINE FM_DEALLOCATE_RM2

```
SUBROUTINE FMEQ_RATIONAL(MA,MB)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: MA,MB
  INTENT (IN) :: MA
  INTENT (INOUT) :: MB
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  CALL IMEQ(MA%NUMERATOR,MB%NUMERATOR)
  CALL IMEQ(MA%DENOMINATOR,MB%DENOMINATOR)
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END SUBROUTINE FMEQ_RATIONAL
```

!

=

```
SUBROUTINE FMEQ_RATIONAL_RMRM(MA,MB)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: MA,MB
  INTENT (INOUT) :: MA
  INTENT (IN) :: MB
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  CALL FMEQ_INDEX_RATIONAL(MA)
  CALL FM_UNDEF_INP(MB)
  CALL FMEQ_RATIONAL(MB,MA)
  CALL FMEQ_RATIONAL_TEMP
  CALL FM_MAX_EXP_RM(MA)
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END SUBROUTINE FMEQ_RATIONAL_RMRM
```

```
SUBROUTINE FMEQ_RATIONAL_RMI(MA,IVAL)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: MA
  INTEGER :: IVAL
  INTENT (INOUT) :: MA
  INTENT (IN) :: IVAL
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  CALL FMEQ_INDEX_RATIONAL(MA)
  CALL IMI2M(IVAL,MA%NUMERATOR)
  CALL IMI2M(1,MA%DENOMINATOR)
  CALL FMEQ_RATIONAL_TEMP
  CALL FM_MAX_EXP_RM(MA)
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END SUBROUTINE FMEQ_RATIONAL_RMI
```

```
SUBROUTINE FMEQ_RATIONAL_RMIM(MA,MB)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL) :: MA
  TYPE (IM) :: MB
  INTENT (INOUT) :: MA
  INTENT (IN) :: MB
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
```

```

CALL FMEQ_INDEX_RATIONAL(MA)
CALL FM_UNDEF_INP(MB)
CALL IMEQ(MB%MIM,MA%NUMERATOR)
CALL IMI2M(1,MA%DENOMINATOR)
CALL FMEQ_RATIONAL_TEMP
CALL FM_MAX_EXP_RM(MA)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END SUBROUTINE FMEQ_RATIONAL_RMIM

```

! Array equal assignments for RM.

! (1) rank 1 = rank 0

```

SUBROUTINE FMEQ_RATIONAL_RM1I(MA,IVAL)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:) :: MA
  INTEGER :: IVAL,J
  INTENT (INOUT) :: MA
  INTENT (IN) :: IVAL
  DO J = 1, SIZE(MA)
    CALL FMEQ_RATIONAL_RMI(MA(J),IVAL)
  ENDDO
END SUBROUTINE FMEQ_RATIONAL_RM1I

```

```

SUBROUTINE FMEQ_RATIONAL_RM1RM(MA,MB)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:) :: MA
  TYPE (FM_RATIONAL) :: MB
  INTEGER :: J
  INTENT (INOUT) :: MA
  INTENT (IN) :: MB
  CALL FMEQ_RATIONAL_RMRM(MT_RM,MB)
  DO J = 1, SIZE(MA)
    CALL FMEQ_RATIONAL_RMRM(MA(J),MT_RM)
  ENDDO
END SUBROUTINE FMEQ_RATIONAL_RM1RM

```

```

SUBROUTINE FMEQ_RATIONAL_RM1IM(MA,MB)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:) :: MA
  TYPE (IM) :: MB
  INTEGER :: J
  INTENT (INOUT) :: MA
  INTENT (IN) :: MB
  CALL IMEQ(MB%MIM,R_1%MIM)
  DO J = 1, SIZE(MA)
    CALL FMEQ_RATIONAL_RMIM(MA(J),R_1)
  ENDDO
END SUBROUTINE FMEQ_RATIONAL_RM1IM

```

! (2) rank 1 = rank 1

```

SUBROUTINE FMEQ_RATIONAL_RM1I1(MA,IVAL)

```



```

USE FMVALS
IMPLICIT NONE
TYPE (FM_RATIONAL), DIMENSION(:) :: MA
INTEGER, DIMENSION(:) :: IVAL
INTEGER :: J
INTENT (INOUT) :: MA
INTENT (IN) :: IVAL
IF (SIZE(MA) /= SIZE(IVAL)) THEN
    TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
    CALL IMST2M('UNKNOWN',MT_RM%NUMERATOR)
    CALL IMST2M('UNKNOWN',MT_RM%DENOMINATOR)
    DO J = 1, SIZE(MA)
        CALL IMEQ(MT_RM%NUMERATOR,MA(J)%NUMERATOR)
        CALL IMEQ(MT_RM%DENOMINATOR,MA(J)%DENOMINATOR)
    ENDDO
    CALL FMEQ_RATIONAL_TEMP
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
ENDIF
DO J = 1, SIZE(MA)
    CALL FMEQ_RATIONAL_RMI(MA(J),IVAL(J))
ENDDO
END SUBROUTINE FMEQ_RATIONAL_RM1I1

```

```

SUBROUTINE FMEQ_RATIONAL_RM1RM1(MA,MB)
USE FMVALS
IMPLICIT NONE
TYPE (FM_RATIONAL), DIMENSION(:) :: MA
TYPE (FM_RATIONAL), DIMENSION(:) :: MB
TYPE (FM_RATIONAL), ALLOCATABLE, DIMENSION(:) :: TEMP
INTEGER :: J,N
INTENT (INOUT) :: MA
INTENT (IN) :: MB
IF (SIZE(MA) /= SIZE(MB)) THEN
    TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
    CALL IMST2M('UNKNOWN',MT_RM%NUMERATOR)
    CALL IMST2M('UNKNOWN',MT_RM%DENOMINATOR)
    DO J = 1, SIZE(MA)
        CALL IMEQ(MT_RM%NUMERATOR,MA(J)%NUMERATOR)
        CALL IMEQ(MT_RM%DENOMINATOR,MA(J)%DENOMINATOR)
    ENDDO
    CALL FMEQ_RATIONAL_TEMP
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
ENDIF
N = SIZE(MA)

```

! To avoid problems when lhs and rhs are overlapping parts of the same array, move MB
! to a temporary array before re-defining any of MA.

```

ALLOCATE(TEMP(N))
CALL FMEQ_INDEX_RATIONAL(TEMP)
DO J = 1, N
    CALL IMEQ(MB(J)%NUMERATOR,TEMP(J)%NUMERATOR)
    CALL IMEQ(MB(J)%DENOMINATOR,TEMP(J)%DENOMINATOR)
ENDDO

```

```

DO J = 1, N
  CALL FMEQ_RATIONAL_RMRM(MA(J),TEMP(J))
ENDDO
CALL FM_DEALLOCATE(TEMP)
DEALLOCATE(TEMP)
END SUBROUTINE FMEQ_RATIONAL_RM1RM1

```

```

SUBROUTINE FMEQ_RATIONAL_RM1IM1(MA,MB)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:) :: MA
  TYPE (IM), DIMENSION(:) :: MB
  TYPE (IM), ALLOCATABLE, DIMENSION(:) :: TEMP
  INTEGER :: J,N
  INTENT (INOUT) :: MA
  INTENT (IN) :: MB
  IF (SIZE(MA) /= SIZE(MB)) THEN
    TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
    CALL IMST2M('UNKNOWN',MT_RM%NUMERATOR)
    CALL IMST2M('UNKNOWN',MT_RM%DENOMINATOR)
    DO J = 1, SIZE(MA)
      CALL IMEQ(MT_RM%NUMERATOR,MA(J)%NUMERATOR)
      CALL IMEQ(MT_RM%DENOMINATOR,MA(J)%DENOMINATOR)
    ENDDO
    CALL FMEQ_RATIONAL_TEMP
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
  ENDF
  N = SIZE(MA)
  ALLOCATE(TEMP(N))
  CALL FMEQ_INDEX(TEMP)
  DO J = 1, SIZE(MA)
    CALL IMEQ(MB(J)%MIM,TEMP(J)%MIM)
  ENDDO
  DO J = 1, SIZE(MA)
    CALL FMEQ_RATIONAL_RMIM(MA(J),TEMP(J))
  ENDDO
  CALL FM_DEALLOCATE(TEMP)
  DEALLOCATE(TEMP)
END SUBROUTINE FMEQ_RATIONAL_RM1IM1

```

! (3) rank 2 = rank 0

```

SUBROUTINE FMEQ_RATIONAL_RM2I(MA,IVAL)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:, :) :: MA
  INTEGER :: IVAL,J,K
  INTENT (INOUT) :: MA
  INTENT (IN) :: IVAL
  DO J = 1, SIZE(MA,DIM=1)
    DO K = 1, SIZE(MA,DIM=2)
      CALL FMEQ_RATIONAL_RMI(MA(J,K),IVAL)
    ENDDO
  ENDDO
END SUBROUTINE FMEQ_RATIONAL_RM2I

```

```

SUBROUTINE FMEQ_RATIONAL_RM2RM(MA,MB)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:,:) :: MA
  TYPE (FM_RATIONAL) :: MB
  INTEGER :: J,K
  INTENT (INOUT) :: MA
  INTENT (IN) :: MB
  CALL FMEQ_RATIONAL_RMRM(MT_RM,MB)
  DO J = 1, SIZE(MA,DIM=1)
    DO K = 1, SIZE(MA,DIM=2)
      CALL FMEQ_RATIONAL_RMRM(MA(J,K),MT_RM)
    ENDDO
  ENDDO
END SUBROUTINE FMEQ_RATIONAL_RM2RM

```

```

SUBROUTINE FMEQ_RATIONAL_RM2IM(MA,MB)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:,:) :: MA
  TYPE (IM) :: MB
  INTEGER :: J,K
  INTENT (INOUT) :: MA
  INTENT (IN) :: MB
  CALL IMEQ(MB%MIM,R_1%MIM)
  DO J = 1, SIZE(MA,DIM=1)
    DO K = 1, SIZE(MA,DIM=2)
      CALL FMEQ_RATIONAL_RMIM(MA(J,K),R_1)
    ENDDO
  ENDDO
END SUBROUTINE FMEQ_RATIONAL_RM2IM

```

! (4) rank 2 = rank 2

```

SUBROUTINE FMEQ_RATIONAL_RM2I2(MA,IVAL)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:,:) :: MA
  INTEGER, DIMENSION(:,:) :: IVAL
  INTEGER :: J,K
  INTENT (INOUT) :: MA
  INTENT (IN) :: IVAL
  IF (SIZE(MA,DIM=1) /= SIZE(IVAL,DIM=1) .OR. SIZE(MA,DIM=2) /= SIZE(IVAL,DIM=2)) THEN
    TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
    CALL IMST2M('UNKNOWN',MT_RM%NUMERATOR)
    CALL IMST2M('UNKNOWN',MT_RM%DENOMINATOR)
    DO J = 1, SIZE(MA,DIM=1)
      DO K = 1, SIZE(MA,DIM=2)
        CALL IMEQ(MT_RM%NUMERATOR,MA(J,K)%NUMERATOR)
        CALL IMEQ(MT_RM%DENOMINATOR,MA(J,K)%DENOMINATOR)
      ENDDO
    ENDDO
    CALL FMEQ_RATIONAL_TEMP
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
  RETURN

```

```

ENDIF
DO J = 1, SIZE(MA,DIM=1)
  DO K = 1, SIZE(MA,DIM=2)
    CALL FMEQ_RATIONAL_RMI(MA(J,K),IVAL(J,K))
  ENDDO
ENDDO
END SUBROUTINE FMEQ_RATIONAL_RM2I2

```

```

SUBROUTINE FMEQ_RATIONAL_RM2RM2(MA,MB)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM_RATIONAL), DIMENSION(:,:) :: MA
  TYPE (FM_RATIONAL), DIMENSION(:,:) :: MB
  TYPE (FM_RATIONAL), ALLOCATABLE, DIMENSION(:,:) :: TEMP
  INTEGER :: J,K
  INTENT (INOUT) :: MA
  INTENT (IN) :: MB
  CALL FMEQ_INDEX_RATIONAL(MA)
  CALL FM_UNDEF_INP(MB)
  IF (SIZE(MA,DIM=1) /= SIZE(MB,DIM=1) .OR. SIZE(MA,DIM=2) /= SIZE(MB,DIM=2)) THEN
    TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
    CALL IMST2M('UNKNOWN',MT_RM%NUMERATOR)
    CALL IMST2M('UNKNOWN',MT_RM%DENOMINATOR)
    DO J = 1, SIZE(MA,DIM=1)
      DO K = 1, SIZE(MA,DIM=2)
        CALL IMEQ(MT_RM%NUMERATOR,MA(J,K)%NUMERATOR)
        CALL IMEQ(MT_RM%DENOMINATOR,MA(J,K)%DENOMINATOR)
      ENDDO
    ENDDO
    CALL FMEQ_RATIONAL_TEMP
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
    RETURN
  ENDIF

```

! To avoid problems when lhs and rhs are overlapping parts of the same array, move MB
! to a temporary array before re-defining any of MA.

```

ALLOCATE(TEMP(SIZE(MA,DIM=1),SIZE(MA,DIM=2)))
CALL FMEQ_INDEX_RATIONAL(TEMP)
DO J = 1, SIZE(MA,DIM=1)
  DO K = 1, SIZE(MA,DIM=2)
    CALL IMEQ(MB(J,K)%NUMERATOR,TEMP(J,K)%NUMERATOR)
    CALL IMEQ(MB(J,K)%DENOMINATOR,TEMP(J,K)%DENOMINATOR)
  ENDDO
ENDDO
DO J = 1, SIZE(MA,DIM=1)
  DO K = 1, SIZE(MA,DIM=2)
    CALL FMEQ_RATIONAL_RMRM(MA(J,K),TEMP(J,K))
  ENDDO
ENDDO
CALL FM_DEALLOCATE(TEMP)
DEALLOCATE(TEMP)
END SUBROUTINE FMEQ_RATIONAL_RM2RM2

```

```

SUBROUTINE FMEQ_RATIONAL_RM2IM2(MA,MB)
  USE FMVALS

```