

```

! FMZM 1.3                      David M. Smith

! This module extends the definition of the basic Fortran arithmetic and function operations so
! they also apply to multiple precision numbers, using version 1.3 of FM.
! There are three multiple precision data types:
!   FM (multiple precision real)
!   IM (multiple precision integer)
!   ZM (multiple precision complex)

! For some examples and general advice about using these multiple-precision data types, see the
! program SampleFM.f95.

! Most of the functions defined in this module are multiple precision versions of standard Fortran
! functions. In addition, there are functions for direct conversion, formatting, and some
! mathematical special functions.

! TO_FM is a function for converting other types of numbers to type FM. Note that TO_FM(3.12)
! converts the REAL constant to FM, but it is accurate only to single precision, since the number
! 3.12 cannot be represented exactly in binary and has already been rounded to single precision.
! Similarly, TO_FM(3.12D0) agrees with 3.12 to double precision accuracy, and TO_FM('3.12') or
! TO_FM(312)/TO_FM(100) agrees to full FM accuracy.

! TO_IM converts to type IM, and TO_ZM converts to type ZM.

! Functions are also supplied for converting the three multiple precision types to the other
! numeric data types:
!   TO_INT  converts to machine precision integer
!   TO_SP   converts to single precision
!   TO_DP   converts to double precision
!   TO_SPZ  converts to single precision complex
!   TO_DPZ  converts to double precision complex

! WARNING:  When multiple precision type declarations are inserted in an existing program, take
! care in converting functions like DBLE(X), where X has been declared as a multiple
! precision type. If X was single precision in the original program, then replacing
! the DBLE(X) by TO_DP(X) in the new version could lose accuracy. For this reason, the
! Fortran type-conversion functions defined in this module assume that results should
! be multiple precision whenever inputs are. Examples:
!   DBLE(TO_FM('1.23E+123456'))      is type FM
!   REAL(TO_FM('1.23E+123456'))      is type FM
!   REAL(TO_ZM('3.12+4.56i'))        is type FM   = TO_FM('3.12')
!   INT(TO_FM('1.23'))                is type IM   = TO_IM(1)
!   INT(TO_IM('1E+23'))               is type IM
!   CMPLX(TO_FM('1.23'),TO_FM('4.56')) is type ZM

! IS_OVERFLOW, IS_UNDERFLOW, and IS_UNKNOWN are logical functions for checking whether a multiple
! precision number is in one of the exception categories. Testing to see if a type FM number is
! in the +overflow category by directly using an IF can be tricky. When MAFM is +overflow, the
! statement
!       IF (MAFM == TO_FM(' +OVERFLOW ')) THEN
! will return false, since the comparison routine cannot be sure that two different overflowed
! results would have been equal if the overflow threshold had been higher. Instead, use

```

! IF (IS\_OVERFLOW(MAFM)) THEN  
! which will be true if MAFM is + or - overflow.

! Programs using this module may sometimes need to call FM, IM, or ZM routines directly. This  
! is normally the case when routines are needed that are not Fortran intrinsics, such as the  
! formatting subroutine FM\_FORM. In a program using this module, suppose MAFM has been declared  
! with TYPE (FM) :: MAFM. To convert the number to a character string with F65.60 format, use  
! CALL FM\_FORM('F65.60',MAFM,ST1)

! WARNING: To be safe, all multiple precision variables in a user's program should be declared  
! as type (FM), (IM), or (ZM), and any direct calls to subroutines should be the kind  
! with the underscore. Subroutines that define one or more multiple precision output  
! values, such as computing pi using  
! CALL FM\_PI(PI)  
! automatically cause PI to be put into the FM saved variable area of storage. Calling  
! the low-level routine ( CALL FMPI(PI%MFM) ) would cause PI to be treated as an FM  
! temporary variable if PI had not been previously defined in the program. Then the  
! value of PI could be discarded before the program is finished using it.

! In subroutine or function subprograms all multiple precision variables that are local to that  
! routine should be declared with the SAVE attribute. It is not an error to omit SAVE, but if  
! the compiler creates new copies of the variables for each call to the routine, then the program  
! will leak memory.

! Type (FM), (IM), or (ZM) variables cannot have their multiple precision values initialized in  
! the declaration statement, as can ordinary variables. If the original program had

! DOUBLE PRECISION :: X = 2.3D0  
! then the corresponding FM version would have  
! TYPE (FM), SAVE :: X  
! ... (other declarations) ...  
! X = TO\_FM( '2.3' )  
!

! An attempt to use a multiple precision variable that has not been defined will be detected by  
! the routines in this module and an error message printed.  
!

! For each of the operations =, ==, /=, <, <=, >, >=, +, -, \*, /, and \*\*, the interface  
! module defines all mixed mode variations involving one of the three multiple precision derived  
! types and another argument having one of the types: { integer, real, double, complex, complex  
! double, FM, IM, ZM }. So mixed mode expressions such as

! MAFM = 12  
! MAFM = MAFM + 1  
! IF (ABS(MAFM) > 1.0D-23) THEN  
! are handled correctly.

! Not all the named functions are defined for all three multiple precision derived types, so the  
! list below shows which can be used. The labels "real", "integer", and "complex" refer to types  
! FM, IM, and ZM respectively, "string" means the function accepts character strings (e.g.,  
! TO\_FM('3.45')), and "other" means the function can accept any of the machine precision data  
! types integer, real, double, complex, or complex double. For functions that accept two or more  
! arguments, like ATAN2 or MAX, all the arguments must be of the same type.

! Note that TO\_ZM also has a 2-argument form: TO\_ZM(2,3) for getting 2 + 3\*i.  
! CMPLX can be used for that, as in CMPLX( TO\_FM(2) , TO\_FM(3) ), but the 2-argument form is  
! more concise. The 2-argument form is available for machine precision integer, single and  
! double precision real pairs. For others, such as X and Y being type(fm), just use CMPLX(X,Y).

! Fortran's 2-argument version of atan(x,y) is also provided. It is the same as the older atan2.

! AVAILABLE FUNCTIONS:

```
! =
! +
! -
! *
! /
! **
! ==
! /=
! <
! <=
! >
! >=
! ABS      real      integer  complex
! ACOS     real      integer  complex
! ACOSH    real      integer  complex
! AIMAG    real      integer  complex
! AINT     real      integer  complex
! ANINT    real      integer  complex
! ASIN     real      integer  complex
! ASINH    real      integer  complex
! ATAN     real      integer  complex
! ATAN2    real      integer  complex
! ATANH    real      integer  complex
! BTEST    real      integer  complex
! CEILING  real      integer  complex
! CMLPX    real      integer  complex
! CONJG    real      integer  complex
! COS      real      integer  complex
! COSH     real      integer  complex
! DBLE     real      integer  complex
! DIGITS   real      integer  complex
! DIM      real      integer  complex
! DINT     real      integer  complex
! EPSILON  real      integer  complex
! EXP      real      integer  complex
! EXPONENT real      integer  complex
! FLOOR    real      integer  complex
! FRACTION real      integer  complex
! HUGE     real      integer  complex
! HYPOT    real      integer  complex
! INT      real      integer  complex
! LOG      real      integer  complex
! LOG10    real      integer  complex
! MAX      real      integer  complex
! MAXEXPONENT real    integer  complex
! MIN      real      integer  complex
! MINEXPONENT real    integer  complex
! MOD      real      integer  complex
! MODULO   real      integer  complex
! NEAREST  real      integer  complex
! NINT     real      integer  complex
```

!	NORM2	real				
!	PRECISION	real		complex		
!	RADIX	real	integer	complex		
!	RANGE	real	integer	complex		
!	REAL	real	integer	complex		
!	RRSPACING	real				
!	SCALE	real		complex		
!	SETEXPONENT	real				
!	SIGN	real	integer			
!	SIN	real		complex		
!	SINH	real		complex		
!	SPACING	real				
!	SQRT	real		complex		
!	TAN	real		complex		
!	TANH	real		complex		
!	TINY	real	integer	complex		
!	TO_FM	real	integer	complex	string	other
!	TO_IM	real	integer	complex	string	other
!	TO_ZM	real	integer	complex	string	other
!	TO_INT	real	integer	complex		
!	TO_SP	real	integer	complex		
!	TO_DP	real	integer	complex		
!	TO_SPZ	real	integer	complex		
!	TO_DPZ	real	integer	complex		
!	IS_OVERFLOW	real	integer	complex		
!	IS_UNDERFLOW	real	integer	complex		
!	IS_UNKNOWN	real	integer	complex		

! SUBROUTINES THAT DO NOT CORRESPOND TO ANY FUNCTION ABOVE:

! 1. Type (FM). MA, MB, MC refer to type (FM) numbers.

! FM\_COSH\_SINH(MA,MB,MC) MB = COSH(MA), MC = SINH(MA)  
! Faster than making two separate calls.

! FM\_COS\_SIN(MA,MB,MC) MB = COS(MA), MC = SIN(MA)  
! Faster than making two separate calls.

! FM\_EULER(MA) MA = Euler's constant ( 0.5772156649... )

! FM\_FLAG(K) K = KFLAG get the value of the FM condition flag -- stored in  
! the internal FM variable KFLAG in module FMVALS.

! FM\_FORM(FORM,MA,STRING) MA is converted to a character string using format FORM and  
! returned in STRING. FORM can represent I, F, E, or ES formats.  
! Example:  
! CALL FMFORM('F60.40',MA,STRING)

! FM\_FPRINT(FORM,MA) Print MA on unit KW using FORM format.

! FM\_PI(MA) MA = pi

! FM\_PRINT(MA) Print MA on unit KW using current format.

! FM\_RANDOM\_NUMBER(X) X is returned as a double precision random number, uniformly

```

! distributed on the open interval (0,1). It is a high-quality,
! long-period generator based on 49-digit prime numbers.
! Note that X is double precision, unlike the similar Fortran
! intrinsic random number routine, which returns a single-precision
! result. A default initial seed is used if FM_RANDOM_NUMBER is
! called without calling FM_RANDOM_SEED_PUT first.

! FM_RANDOM_SEED_GET(SEED) returns the seven integers SEED(1) through SEED(7) as the current
! seed for the FM_RANDOM_NUMBER generator.

! FM_RANDOM_SEED_PUT(SEED) initializes the FM_RANDOM_NUMBER generator using the seven integers
! SEED(1) through SEED(7). These get and put functions are slower
! than FM_RANDOM_NUMBER, so FM_RANDOM_NUMBER should be called many
! times between FM_RANDOM_SEED_PUT calls. Also, some generators that
! used a 9-digit modulus have failed randomness tests when used with
! only a few numbers being generated between calls to re-start with
! a new seed.

! FM_RANDOM_SEED_SIZE(SIZE) returns integer SIZE as the size of the SEED array used by the
! FM_RANDOM_NUMBER generator. Currently, SIZE = 7.

! FM_RATIONAL_POWER(MA,K,J,MB)
! MB = MA**(K/J) Rational power.
! Faster than MB = MA**(TO_FM(K)/J) for functions like the cube root.

! FM_READ(KREAD,MA) MA is returned after reading one (possibly multi-line) FM number
! on unit KREAD. This routine reads numbers written by FM_WRITE.

! FM_SET(NPREC) Set the internal FM variables so that the precision is at least
! NPREC base 10 digits plus three base 10 guard digits.

! FM_SETVAR(String) Define a new value for one of the internal FM variables in module
! FMVALS that controls one of the FM options. STRING has the form
! variable = value.
! Example: To change the screen width for FM output:
! CALL FM_SETVAR(' KSWIDE = 120 ')
! The variables that can be changed and the options they control are
! listed in sections 2 through 6 of the comments at the top of the
! FM.f95 file. Only one variable can be set per call. The variable
! name in STRING must have no embedded blanks. The value part of
! STRING can be in any numerical format, except in the case of
! variable CMCHAR, which is character type. To set CMCHAR to 'E',
! don't use any quotes in STRING:
! CALL FM_SETVAR(' CMCHAR = E ')

! FM_ULP(MA,MB) MB = One Unit in the Last Place of MA. For positive MA this is the
! same as the Fortran function SPACING, but MB < 0 if MA < 0.
! Examples: If MBASE = 10 and NDIG = 30, then ulp(1.0) =
! 1.0E-29, ulp(-4.5E+67) = -1.0E+38.

! FM_VARS Write the current values of the internal FM variables on unit KW.

! FM_WRITE(KWRITE,MA) Write MA on unit KWRITE.
! Multi-line numbers will have '&' as the last nonblank character
! on all but the last line. These numbers can then be read easily

```

```

!           using FM_READ.

! 2. Type (IM).   MA, MB, MC refer to type (IM) numbers.

!   IM_DIVR(MA,MB,MC,MD)   MC = int(MA/MB),   MD = MA mod MB
!                           When both the quotient and remainder are needed, this routine
!                           is twice as fast as doing MC = MA/MB and MD = MOD(MA,MB)
!                           separately.

!   IM_DVIR(MA,IVAL,MB,IREM)  MB = int(MA/IVAL),   IREM = MA mod IVAL
!                           IVAL and IREM are one word integers.  Faster than doing separately.

!   IM_FORM(FORM,MA,STRING)  MA is converted to a character string using format FORM and
!                           returned in STRING.  FORM can represent I, F, E, or ES formats.
!                           Example: CALL IMFORM('I70',MA,STRING)

!   IM_FPRINT(FORM,MA)       Print MA on unit KW using FORM format.

!   IM_PRINT(MA)             Print MA on unit KW.

!   IM_READ(KREAD,MA)        MA is returned after reading one (possibly multi-line) IM number
!                           on unit KREAD.  This routine reads numbers written by IM_WRITE.

!   IM_WRITE(KWRITE,MA)      Write MA on unit KWRITE.  Multi-line numbers will have '&' as the
!                           last nonblank character on all but the last line.
!                           These numbers can then be read easily using IM_READ.

! 3. Type (ZM).   MA, MB, MC refer to type (ZM) numbers.  MBFM is type (FM).

!   ZM_ARG(MA,MBFM)          MBFM = complex argument of MA.  MBFM is the (real) angle in the
!                           interval ( -pi , pi ] from the positive real axis to the
!                           point (x,y) when MA = x + y*i.

!   ZM_COSH_SINH(MA,MB,MC)   MB = COSH(MA),   MC = SINH(MA).
!                           Faster than 2 calls.

!   ZM_COS_SIN(MA,MB,MC)    MB = COS(MA),   MC = SIN(MA).
!                           Faster than 2 calls.

!   ZM_FORM(FORM1,FORM2,MA,STRING)
!                           STRING = MA
!                           MA is converted to a character string using format FORM1 for the
!                           real part and FORM2 for the imaginary part.  The result is returned
!                           in STRING.  FORM1 and FORM2 can represent I, F, E, or ES formats.
!                           Example:
!                           CALL ZMFORM('F20.10','F15.10',MA,STRING)

!   ZM_FPRINT(FORM1,FORM2,MA) Print MA on unit KW using formats FORM1 and FORM2.

!   ZM_PRINT(MA)             Print MA on unit KW using current format.

!   ZM_READ(KREAD,MA)        MA is returned after reading one (possibly multi-line) ZM number
!                           on unit KREAD.  This routine reads numbers written by ZMWRITE.

```

```

! ZM_RATIONAL_POWER(MA,IVAL,JVAL,MB)
!                               MB = MA ** (IVAL/JVAL)
!                               Faster than MB = MA**(TO_FM(K)/J) for functions like the cube root.
!
! ZM_WRITE(KWRITE,MA)           Write MA on unit KWRITE. Multi-line numbers are formatted for
!                               automatic reading with ZMREAD.

```

```

! Some other functions are defined that do not correspond to machine precision intrinsic
! functions. These include formatting functions, integer modular functions and GCD, and some
! mathematical special functions.
! N, K below are machine precision integers, J1, J2, J3 are TYPE (IM), FMT, FMTR, FMTI are
! character strings, A, B, X are TYPE (FM), and Z is TYPE (ZM).
! The three formatting functions return a character string containing the formatted number, the
! three TYPE (IM) functions return a TYPE (IM) result, and the 12 special functions return
! TYPE (FM) results.

```

```

! Formatting functions:

```

```

! FM_FORMAT(FMT,A)             Put A into FMT (real) format
! IM_FORMAT(FMT,J1)            Put J1 into FMT (integer) format
! ZM_FORMAT(FMTR,FMTI,Z)       Put Z into (complex) format, FMTR for the real
!                               part and FMTI for the imaginary part

```

```

! Examples:

```

```

! ST = FM_FORMAT('F65.60',A)
! WRITE (*,*) ' A = ',TRIM(ST)
! ST = FM_FORMAT('E75.60',B)
! WRITE (*,*) ' B = ',ST(1:75)
! ST = IM_FORMAT('I50',J1)
! WRITE (*,*) ' J1 = ',ST(1:50)
! ST = ZM_FORMAT('F35.30','F30.25',Z)
! WRITE (*,*) ' Z = ',ST(1:70)

```

```

! These functions are used for one-line output. The returned character strings are of
! length 200.

```

```

! For higher precision numbers, the output can be broken onto multiple lines automatically by
! calling subroutines FM_PRINT, IM_PRINT, ZM_PRINT, or the line breaks can be done by hand after
! calling one of the subroutines FM_FORM, IM_FORM, ZM_FORM.

```

```

! For ZM_FORMAT the length of the output is 5 more than the sum of the two field widths.

```

```

! Integer functions:

```

```

! BINOMIAL(N,K)                Binomial coefficient N choose K. Returns the exact result as a
!                               type IM value.
! BINOMIAL(J1,J2)              Binomial coefficient J1 choose J2. Like factorial below, the result
!                               might be too large unless min(J2,J1-J2) is fairly small,
! FACTORIAL(N)                  N! Returns the exact result as a type IM value.
! FACTORIAL(J1)                 J1! Note that the factorial function grows so rapidly that if type IM
!                               variable J1 is larger than the largest machine precision integer,
!                               then J1! has over 10 billion digits and the calculation would
!                               likely fail due to memory or time constraints. This version is
!                               provided for convenience, and will return UNKNOWN if J1 cannot
!                               be represented as a machine precision integer.

```





```

!      J = J * K           ! Set J(i) = J(i) * K(i) for i = 1, ..., 10
!      B = A - K           ! Mixed-mode operations are ok
!      C = 7.3D0 * C - ( C + 2*L )/3

```

```

!      Array functions:

```

```

!      DOT_PRODUCT(X,Y)    Dot product of rank 1 vectors of the same type.
!                          Note that when X and Y are complex, the result is not just the sum
!                          of the products of the corresponding array elements, as it is for
!                          types FM and IM. For ZM the formula is the sum of
!                          conjg(X(j)) * Y(j).
!      IS_OVERFLOW(X)      Returns true if any element is + or - overflow.
!      IS_UNDERFLOW(X)    Returns true if any element is + or - underflow.
!      IS_UNKNOWN(X)      Returns true if any element is unknown.
!      MATMUL(X,Y)        Matrix multiplication of arrays of the same type
!                          Cases for valid argument shapes:
!                          (1) (n,m) * (m,k) --> (n,k)
!                          (2)  (m) * (m,k) --> (k)
!                          (3) (n,m) * (m)  --> (n)
!      MAXLOC(X)           Location of the maximum value in the array
!      MAXVAL(X)           Maximum value in the array
!      MINLOC(X)           Location of the minimum value in the array
!      MINVAL(X)           Minimum value in the array
!      PRODUCT(X)          Product of all values in the array
!      SUM(X)              Sum of all values in the array
!      TRANSPOSE(X)        Matrix transposition. If X is a rank 2 array with shape (n,m), then
!                          Y = TRANSPOSE(X) has shape (m,n) with Y(i,j) = X(j,i).
!      TO_FM(X)            Rank 1 or 2 arrays are converted to similar type (fm) arrays.
!      TO_IM(X)            Rank 1 or 2 arrays are converted to similar type (im) arrays.
!      TO_ZM(X)            Rank 1 or 2 arrays are converted to similar type (zm) arrays.
!      TO_INT(X)           Rank 1 or 2 arrays are converted to similar integer arrays.
!      TO_SP(X)            Rank 1 or 2 arrays are converted to similar single precision arrays.
!      TO_DP(X)            Rank 1 or 2 arrays are converted to similar double precision arrays.
!      TO_SPZ(X)           Rank 1 or 2 arrays are converted to similar single complex arrays.
!      TO_DPZ(X)           Rank 1 or 2 arrays are converted to similar double complex arrays.

```

```

!      The arithmetic array functions DOT_PRODUCT, MATMUL, PRODUCT, and SUM work like the other
!      functions in the FM package in that they raise precision and compute the sums and/or products
!      at the higher precision, then round the final result back to the user's precision to provide
!      a more accurate result.

```

```

!      Fortran's optional [,mask] argument for these functions is not provided.

```

```

!      Many of the 1-argument functions can be used with array arguments, with the result being an
!      array of the same size and shape where the function has been applied to each element.

```

```

!      Examples:

```

```

!      TYPE (FM), SAVE, DIMENSION(10) :: A, B, C
!      ...
!      A = ABS(B)           ! Set A(i) = ABS(B(i)) for i = 1, ..., 10
!      C = SQRT(A+4+B*B)    ! Set C(i) = SQRT(A(i)+4+B(i)*B(i)) for i = 1, ..., 10

```

```

!      Functions that can have array arguments. As above, "real", "integer", and "complex" refer
!      to types FM, IM, and ZM respectively.

```

```

!      ABS                real    integer    complex

```

```

!   ACOS          real          complex
!   ACOSH         real          complex
!   AIMAG         complex
!   AINT          real          complex
!   ANINT         real          complex
!   ASIN          real          complex
!   ASINH         real          complex
!   ATAN          real          complex
!   ATANH         real          complex
!   CEILING       real          integer complex
!   CONJG         complex
!   COS           real          complex
!   COSH          real          complex
!   EXP           real          complex
!   FLOOR         real          integer complex
!   FRACTION      real          complex
!   INT           real          integer complex
!   LOG           real          complex
!   LOG10         real          complex
!   NINT          real          integer complex
!   SIN           real          complex
!   SINH          real          complex
!   SQRT          real          complex
!   TAN           real          complex
!   TANH          real          complex
!   COS_INTEGRAL real
!   COSH_INTEGRAL real
!   ERF           real
!   ERFC          real
!   ERFC_SCALED  real
!   EXP_INTEGRAL_EI real
!   FACTORIAL     real          integer          machine-precision integer
!   FRESNEL_C     real
!   FRESNEL_S     real
!   GAMMA         real
!   LOG_ERFC      real
!   LOG_GAMMA     real
!   LOG_INTEGRAL real
!   PSI           real
!   SIN_INTEGRAL real
!   SINH_INTEGRAL real

```

```

TYPE FM
  INTEGER :: MFM = -1
END TYPE

```

```

TYPE IM
  INTEGER :: MIM = -1
END TYPE

```

```

TYPE ZM
  INTEGER :: MZM(2) = -1
END TYPE

```

```

!           Work variables for derived type operations.

```

```
INTEGER, SAVE :: MTFM = -3
INTEGER, SAVE :: MUFM = -3
INTEGER, SAVE :: MVFM = -3
INTEGER, SAVE :: M1FM = -3
INTEGER, SAVE :: M2FM = -3
INTEGER, SAVE :: M3FM = -3
INTEGER, SAVE :: MTIM = -3
INTEGER, SAVE :: MUIM = -3
INTEGER, SAVE :: MVIM = -3
INTEGER, SAVE :: M1IM = -3
INTEGER, SAVE :: M2IM = -3
INTEGER, SAVE :: M3IM = -3
INTEGER, SAVE :: M01 = -3
INTEGER, SAVE :: MTZM(2) = (/ -3, -3 /)
INTEGER, SAVE :: MUZM(2) = (/ -3, -3 /)
INTEGER, SAVE :: MVZM(2) = (/ -3, -3 /)
INTEGER, SAVE :: M1ZM(2) = (/ -3, -3 /)
INTEGER, SAVE :: M2ZM(2) = (/ -3, -3 /)
INTEGER, SAVE :: M3ZM(2) = (/ -3, -3 /)
INTEGER, SAVE :: MZ01(2) = (/ -3, -3 /)
INTEGER, SAVE :: MZ02(2) = (/ -3, -3 /)
TYPE(FM), SAVE :: MT_FM = FM(-3)
TYPE(IM), SAVE :: MT_IM = IM(-3)
TYPE(ZM), SAVE :: MT_ZM = ZM( / -3, -3 /) )
```

```
INTERFACE TO_FM
```

```
MODULE PROCEDURE FM_I
MODULE PROCEDURE FM_R
MODULE PROCEDURE FM_D
MODULE PROCEDURE FM_Z
MODULE PROCEDURE FM_ZD
MODULE PROCEDURE FM_FM
MODULE PROCEDURE FM_IM
MODULE PROCEDURE FM_ZM
MODULE PROCEDURE FM_ST
MODULE PROCEDURE FM_I1
MODULE PROCEDURE FM_R1
MODULE PROCEDURE FM_D1
MODULE PROCEDURE FM_Z1
MODULE PROCEDURE FM_ZD1
MODULE PROCEDURE FM_FM1
MODULE PROCEDURE FM_IM1
MODULE PROCEDURE FM_ZM1
MODULE PROCEDURE FM_ST1
MODULE PROCEDURE FM_I2
MODULE PROCEDURE FM_R2
MODULE PROCEDURE FM_D2
MODULE PROCEDURE FM_Z2
MODULE PROCEDURE FM_ZD2
MODULE PROCEDURE FM_FM2
MODULE PROCEDURE FM_IM2
MODULE PROCEDURE FM_ZM2
MODULE PROCEDURE FM_ST2
```

```
END INTERFACE
```

```
INTERFACE TO_IM
  MODULE PROCEDURE IM_I
  MODULE PROCEDURE IM_R
  MODULE PROCEDURE IM_D
  MODULE PROCEDURE IM_Z
  MODULE PROCEDURE IM_C
  MODULE PROCEDURE IM_FM
  MODULE PROCEDURE IM_IM
  MODULE PROCEDURE IM_ZM
  MODULE PROCEDURE IM_ST
  MODULE PROCEDURE IM_I1
  MODULE PROCEDURE IM_R1
  MODULE PROCEDURE IM_D1
  MODULE PROCEDURE IM_Z1
  MODULE PROCEDURE IM_C1
  MODULE PROCEDURE IM_FM1
  MODULE PROCEDURE IM_IM1
  MODULE PROCEDURE IM_ZM1
  MODULE PROCEDURE IM_ST1
  MODULE PROCEDURE IM_I2
  MODULE PROCEDURE IM_R2
  MODULE PROCEDURE IM_D2
  MODULE PROCEDURE IM_Z2
  MODULE PROCEDURE IM_C2
  MODULE PROCEDURE IM_FM2
  MODULE PROCEDURE IM_IM2
  MODULE PROCEDURE IM_ZM2
  MODULE PROCEDURE IM_ST2
END INTERFACE
```

```
INTERFACE TO_ZM
  MODULE PROCEDURE ZM_I
  MODULE PROCEDURE ZM2_I
  MODULE PROCEDURE ZM_R
  MODULE PROCEDURE ZM2_R
  MODULE PROCEDURE ZM_D
  MODULE PROCEDURE ZM2_D
  MODULE PROCEDURE ZM_Z
  MODULE PROCEDURE ZM_C
  MODULE PROCEDURE ZM_FM
  MODULE PROCEDURE ZM_IM
  MODULE PROCEDURE ZM_ZM
  MODULE PROCEDURE ZM_ST
  MODULE PROCEDURE ZM_I1
  MODULE PROCEDURE ZM_R1
  MODULE PROCEDURE ZM_D1
  MODULE PROCEDURE ZM_Z1
  MODULE PROCEDURE ZM_C1
  MODULE PROCEDURE ZM_FM1
  MODULE PROCEDURE ZM_IM1
  MODULE PROCEDURE ZM_ZM1
  MODULE PROCEDURE ZM_ST1
  MODULE PROCEDURE ZM_I2
  MODULE PROCEDURE ZM_R2
  MODULE PROCEDURE ZM_D2
  MODULE PROCEDURE ZM_Z2
```

```
MODULE PROCEDURE ZM_C2
MODULE PROCEDURE ZM_FM2
MODULE PROCEDURE ZM_IM2
MODULE PROCEDURE ZM_ZM2
MODULE PROCEDURE ZM_ST2
END INTERFACE
```

```
INTERFACE TO_INT
MODULE PROCEDURE FM_2INT
MODULE PROCEDURE IM_2INT
MODULE PROCEDURE ZM_2INT
MODULE PROCEDURE FM_2INT1
MODULE PROCEDURE IM_2INT1
MODULE PROCEDURE ZM_2INT1
MODULE PROCEDURE FM_2INT2
MODULE PROCEDURE IM_2INT2
MODULE PROCEDURE ZM_2INT2
END INTERFACE
```

```
INTERFACE TO_SP
MODULE PROCEDURE FM_2SP
MODULE PROCEDURE IM_2SP
MODULE PROCEDURE ZM_2SP
MODULE PROCEDURE FM_2SP1
MODULE PROCEDURE IM_2SP1
MODULE PROCEDURE ZM_2SP1
MODULE PROCEDURE FM_2SP2
MODULE PROCEDURE IM_2SP2
MODULE PROCEDURE ZM_2SP2
END INTERFACE
```

```
INTERFACE TO_DP
MODULE PROCEDURE FM_2DP
MODULE PROCEDURE IM_2DP
MODULE PROCEDURE ZM_2DP
MODULE PROCEDURE FM_2DP1
MODULE PROCEDURE IM_2DP1
MODULE PROCEDURE ZM_2DP1
MODULE PROCEDURE FM_2DP2
MODULE PROCEDURE IM_2DP2
MODULE PROCEDURE ZM_2DP2
END INTERFACE
```

```
INTERFACE TO_SPZ
MODULE PROCEDURE FM_2SPZ
MODULE PROCEDURE IM_2SPZ
MODULE PROCEDURE ZM_2SPZ
MODULE PROCEDURE FM_2SPZ1
MODULE PROCEDURE IM_2SPZ1
MODULE PROCEDURE ZM_2SPZ1
MODULE PROCEDURE FM_2SPZ2
MODULE PROCEDURE IM_2SPZ2
MODULE PROCEDURE ZM_2SPZ2
END INTERFACE
```

```
INTERFACE TO_DPZ
```

```
MODULE PROCEDURE FM_2DPZ
MODULE PROCEDURE IM_2DPZ
MODULE PROCEDURE ZM_2DPZ
MODULE PROCEDURE FM_2DPZ1
MODULE PROCEDURE IM_2DPZ1
MODULE PROCEDURE ZM_2DPZ1
MODULE PROCEDURE FM_2DPZ2
MODULE PROCEDURE IM_2DPZ2
MODULE PROCEDURE ZM_2DPZ2
END INTERFACE
```

```
INTERFACE IS_OVERFLOW
MODULE PROCEDURE FM_IS_OVERFLOW
MODULE PROCEDURE IM_IS_OVERFLOW
MODULE PROCEDURE ZM_IS_OVERFLOW
MODULE PROCEDURE FM_IS_OVERFLOW1
MODULE PROCEDURE IM_IS_OVERFLOW1
MODULE PROCEDURE ZM_IS_OVERFLOW1
MODULE PROCEDURE FM_IS_OVERFLOW2
MODULE PROCEDURE IM_IS_OVERFLOW2
MODULE PROCEDURE ZM_IS_OVERFLOW2
END INTERFACE
```

```
INTERFACE IS_UNDERFLOW
MODULE PROCEDURE FM_IS_UNDERFLOW
MODULE PROCEDURE IM_IS_UNDERFLOW
MODULE PROCEDURE ZM_IS_UNDERFLOW
MODULE PROCEDURE FM_IS_UNDERFLOW1
MODULE PROCEDURE IM_IS_UNDERFLOW1
MODULE PROCEDURE ZM_IS_UNDERFLOW1
MODULE PROCEDURE FM_IS_UNDERFLOW2
MODULE PROCEDURE IM_IS_UNDERFLOW2
MODULE PROCEDURE ZM_IS_UNDERFLOW2
END INTERFACE
```

```
INTERFACE IS_UNKNOWN
MODULE PROCEDURE FM_IS_UNKNOWN
MODULE PROCEDURE IM_IS_UNKNOWN
MODULE PROCEDURE ZM_IS_UNKNOWN
MODULE PROCEDURE FM_IS_UNKNOWN1
MODULE PROCEDURE IM_IS_UNKNOWN1
MODULE PROCEDURE ZM_IS_UNKNOWN1
MODULE PROCEDURE FM_IS_UNKNOWN2
MODULE PROCEDURE IM_IS_UNKNOWN2
MODULE PROCEDURE ZM_IS_UNKNOWN2
END INTERFACE
```

```
INTERFACE FMEQ_INDEX
MODULE PROCEDURE FMEQ_INDEX_FM0
MODULE PROCEDURE FMEQ_INDEX_FM1
MODULE PROCEDURE FMEQ_INDEX_FM2
MODULE PROCEDURE FMEQ_INDEX_IM0
MODULE PROCEDURE FMEQ_INDEX_IM1
MODULE PROCEDURE FMEQ_INDEX_IM2
MODULE PROCEDURE FMEQ_INDEX_ZM0
MODULE PROCEDURE FMEQ_INDEX_ZM1
```

```
MODULE PROCEDURE FMEQ_INDEX_ZM2
END INTERFACE
```

```
INTERFACE FM_UNDEF_INP
MODULE PROCEDURE FM_UNDEF_INP_FM0
MODULE PROCEDURE FM_UNDEF_INP_IM0
MODULE PROCEDURE FM_UNDEF_INP_ZM0
MODULE PROCEDURE FM_UNDEF_INP_FM1
MODULE PROCEDURE FM_UNDEF_INP_IM1
MODULE PROCEDURE FM_UNDEF_INP_ZM1
MODULE PROCEDURE FM_UNDEF_INP_FM2
MODULE PROCEDURE FM_UNDEF_INP_IM2
MODULE PROCEDURE FM_UNDEF_INP_ZM2
END INTERFACE
```

```
INTERFACE FM_DEALLOCATE
MODULE PROCEDURE FM_DEALLOCATE_FM1
MODULE PROCEDURE FM_DEALLOCATE_IM1
MODULE PROCEDURE FM_DEALLOCATE_ZM1
MODULE PROCEDURE FM_DEALLOCATE_FM2
MODULE PROCEDURE FM_DEALLOCATE_IM2
MODULE PROCEDURE FM_DEALLOCATE_ZM2
END INTERFACE
```

CONTAINS

!

TO\_FM

```
FUNCTION FM_I(IVAL)
USE FMVALS
IMPLICIT NONE
TYPE (FM) :: FM_I
INTEGER :: IVAL
INTENT (IN) :: IVAL
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FMI2M(IVAL, FM_I%MFM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_I
```

```
FUNCTION FM_R(R)
USE FMVALS
IMPLICIT NONE
TYPE (FM) :: FM_R
REAL :: R
INTENT (IN) :: R
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FMSP2M(R, FM_R%MFM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_R
```

```
FUNCTION FM_D(D)
USE FMVALS
IMPLICIT NONE
TYPE (FM) :: FM_D
DOUBLE PRECISION :: D
INTENT (IN) :: D
```

```
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FM DP2M(D, FM_D% MFM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_D
```

```
FUNCTION FM_Z(Z)
USE FMVALS
IMPLICIT NONE
TYPE (FM) :: FM_Z
COMPLEX :: Z
INTENT (IN) :: Z
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FM SP2M(REAL(Z), FM_Z% MFM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_Z
```

```
FUNCTION FM_ZD(C)
USE FMVALS
IMPLICIT NONE
TYPE (FM) :: FM_ZD
COMPLEX (KIND(0.0D0)) :: C
INTENT (IN) :: C
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FM DP2M(REAL(C, KIND(0.0D0)), FM_ZD% MFM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_ZD
```

```
FUNCTION FM_FM(MA)
USE FMVALS
IMPLICIT NONE
TYPE (FM) :: FM_FM, MA
INTENT (IN) :: MA
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FM_UNDEF_INP(MA)
CALL FMEQ(MA% MFM, FM_FM% MFM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_FM
```

```
FUNCTION FM_IM(MA)
USE FMVALS
IMPLICIT NONE
TYPE (FM) :: FM_IM
TYPE (IM) :: MA
INTENT (IN) :: MA
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FM_UNDEF_INP(MA)
CALL IMI2FM(MA% MIM, FM_IM% MFM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_IM
```

```
FUNCTION FM_ZM(MA)
USE FMVALS
IMPLICIT NONE
TYPE (FM) :: FM_ZM
TYPE (ZM) :: MA
INTENT (IN) :: MA
```



```
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FM_UNDEF_INP(MA)
CALL ZMREAL(MA%MZM, FM_ZM%MFM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_ZM
```

```
FUNCTION FM_ST(ST)
USE FMVALS
IMPLICIT NONE
TYPE (FM) :: FM_ST
CHARACTER(*) :: ST
INTENT (IN) :: ST
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FMST2M(ST, FM_ST%MFM)
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_ST
```

```
FUNCTION FM_I1(IVAL)
USE FMVALS
IMPLICIT NONE
INTEGER, DIMENSION(:) :: IVAL
TYPE (FM), DIMENSION(SIZE(IVAL)) :: FM_I1
INTEGER :: J, N
INTENT (IN) :: IVAL
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
N = SIZE(IVAL)
DO J = 1, N
    CALL FMI2M(IVAL(J), FM_I1(J)%MFM)
ENDDO
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_I1
```

```
FUNCTION FM_R1(R)
USE FMVALS
IMPLICIT NONE
REAL, DIMENSION(:) :: R
TYPE (FM), DIMENSION(SIZE(R)) :: FM_R1
INTEGER :: J, N
INTENT (IN) :: R
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
N = SIZE(R)
DO J = 1, N
    CALL FMSP2M(R(J), FM_R1(J)%MFM)
ENDDO
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_R1
```

```
FUNCTION FM_D1(D)
USE FMVALS
IMPLICIT NONE
DOUBLE PRECISION, DIMENSION(:) :: D
TYPE (FM), DIMENSION(SIZE(D)) :: FM_D1
INTEGER :: J, N
INTENT (IN) :: D
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
N = SIZE(D)
```

```

DO J = 1, N
  CALL FMDP2M(D(J),FM_D1(J)%MFM)
ENDDO
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_D1

```

```

FUNCTION FM_Z1(Z)
  USE FMVALS
  IMPLICIT NONE
  COMPLEX, DIMENSION(:) :: Z
  TYPE (FM), DIMENSION(SIZE(Z)) :: FM_Z1
  INTEGER :: J,N
  INTENT (IN) :: Z
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  N = SIZE(Z)
  DO J = 1, N
    CALL FMSP2M(REAL(Z(J)),FM_Z1(J)%MFM)
  ENDDO
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_Z1

```

```

FUNCTION FM_ZD1(C)
  USE FMVALS
  IMPLICIT NONE
  COMPLEX (KIND(0.0D0)), DIMENSION(:) :: C
  TYPE (FM), DIMENSION(SIZE(C)) :: FM_ZD1
  INTEGER :: J,N
  INTENT (IN) :: C
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  N = SIZE(C)
  DO J = 1, N
    CALL FMDP2M(REAL(C(J),KIND(0.0D0)),FM_ZD1(J)%MFM)
  ENDDO
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_ZD1

```

```

FUNCTION FM_FM1(MA)
  USE FMVALS
  IMPLICIT NONE
  TYPE (FM), DIMENSION(:) :: MA
  TYPE (FM), DIMENSION(SIZE(MA)) :: FM_FM1
  INTEGER :: J,N
  INTENT (IN) :: MA
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  CALL FM_UNDEF_INP(MA)
  N = SIZE(MA)
  DO J = 1, N
    CALL FMEQ(MA(J)%MFM,FM_FM1(J)%MFM)
  ENDDO
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_FM1

```

```

FUNCTION FM_IM1(MA)
  USE FMVALS
  IMPLICIT NONE
  TYPE (IM), DIMENSION(:) :: MA

```

```

TYPE (FM), DIMENSION(SIZE(MA)) :: FM_IM1
INTEGER :: J,N
INTENT (IN) :: MA
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FM_UNDEF_INP(MA)
N = SIZE(MA)
DO J = 1, N
    CALL IMI2FM(MA(J)%MIM,FM_IM1(J)%MFM)
ENDDO
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_IM1

```

```

FUNCTION FM_ZM1(MA)
USE FMVALS
IMPLICIT NONE
TYPE (ZM), DIMENSION(:) :: MA
TYPE (FM), DIMENSION(SIZE(MA)) :: FM_ZM1
INTEGER :: J,N
INTENT (IN) :: MA
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
CALL FM_UNDEF_INP(MA)
N = SIZE(MA)
DO J = 1, N
    CALL ZMREAL(MA(J)%MZM,FM_ZM1(J)%MFM)
ENDDO
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_ZM1

```

```

FUNCTION FM_ST1(ST)
USE FMVALS
IMPLICIT NONE
CHARACTER(*), DIMENSION(:) :: ST
TYPE (FM), DIMENSION(SIZE(ST)) :: FM_ST1
INTEGER :: J,N
INTENT (IN) :: ST
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
N = SIZE(ST)
DO J = 1, N
    CALL FMST2M(ST(J),FM_ST1(J)%MFM)
ENDDO
TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_ST1

```

```

FUNCTION FM_I2(IVAL)
USE FMVALS
IMPLICIT NONE
INTEGER, DIMENSION(:,:) :: IVAL
TYPE (FM), DIMENSION(SIZE(IVAL,DIM=1),SIZE(IVAL,DIM=2)) :: FM_I2
INTEGER :: J,K
INTENT (IN) :: IVAL
TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
DO J = 1, SIZE(IVAL,DIM=1)
    DO K = 1, SIZE(IVAL,DIM=2)
        CALL FMI2M(IVAL(J,K),FM_I2(J,K)%MFM)
    ENDDO
ENDDO

```

```
    TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_I2
```

```
FUNCTION FM_R2(R)
  USE FMVALS
  IMPLICIT NONE
  REAL, DIMENSION(:, :) :: R
  TYPE (FM), DIMENSION(SIZE(R,DIM=1),SIZE(R,DIM=2)) :: FM_R2
  INTEGER :: J,K
  INTENT (IN) :: R
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  DO J = 1, SIZE(R,DIM=1)
    DO K = 1, SIZE(R,DIM=2)
      CALL FMSP2M(R(J,K),FM_R2(J,K)%MFM)
    ENDDO
  ENDDO
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_R2
```

```
FUNCTION FM_D2(D)
  USE FMVALS
  IMPLICIT NONE
  DOUBLE PRECISION, DIMENSION(:, :) :: D
  TYPE (FM), DIMENSION(SIZE(D,DIM=1),SIZE(D,DIM=2)) :: FM_D2
  INTEGER :: J,K
  INTENT (IN) :: D
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  DO J = 1, SIZE(D,DIM=1)
    DO K = 1, SIZE(D,DIM=2)
      CALL FMDP2M(D(J,K),FM_D2(J,K)%MFM)
    ENDDO
  ENDDO
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_D2
```

```
FUNCTION FM_Z2(Z)
  USE FMVALS
  IMPLICIT NONE
  COMPLEX, DIMENSION(:, :) :: Z
  TYPE (FM), DIMENSION(SIZE(Z,DIM=1),SIZE(Z,DIM=2)) :: FM_Z2
  INTEGER :: J,K
  INTENT (IN) :: Z
  TEMPV_CALL_STACK = TEMPV_CALL_STACK + 1
  DO J = 1, SIZE(Z,DIM=1)
    DO K = 1, SIZE(Z,DIM=2)
      CALL FMSP2M(REAL(Z(J,K)),FM_Z2(J,K)%MFM)
    ENDDO
  ENDDO
  TEMPV_CALL_STACK = TEMPV_CALL_STACK - 1
END FUNCTION FM_Z2
```

```
FUNCTION FM_ZD2(C)
  USE FMVALS
  IMPLICIT NONE
  COMPLEX (KIND(0.0D0)), DIMENSION(:, :) :: C
  TYPE (FM), DIMENSION(SIZE(C,DIM=1),SIZE(C,DIM=2)) :: FM_ZD2
```